Authelia CONF

You will need to setup a domain/subdomain for your authentication. Setup your domain/subdomain in NGINX Proxy Manager as normal. Then add the following to the "Advanced" tab in the Proxy Host setup for the domain.

```
location / {
set $upstream_authelia http://192.168.1.25:9091; # This example assumes a Docker deployment.
Change the IP and Port to your setup
proxy pass $upstream authelia;
client body buffer size 128k;
#Timeout if the real server is dead
proxy next upstream error timeout invalid header http 500 http 502 http 503;
# Advanced Proxy Config
send timeout 5m;
proxy read timeout 360;
proxy send timeout 360;
proxy connect timeout 360;
# Basic Proxy Config
proxy set header Host $host;
proxy set header X-Real-IP $remote addr;
proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
proxy set header X-Forwarded-Proto $scheme;
proxy set header X-Forwarded-Host $http host;
proxy set header X-Forwarded-Uri $request uri;
proxy set header X-Forwarded-Ssl on;
proxy redirect http:// $scheme://;
proxy_http_version 1.1;
proxy_set_header Connection "";
proxy cache bypass $cookie session;
proxy_no_cache $cookie_session;
proxy buffers 64 256k;
# If behind reverse proxy, forwards the correct IP, assumes you're using Cloudflare. Adjust IP
for your Docker network.
```

```
set_real_ip_from 192.168.1.0/24; #make sure this IP range matches your netowrk setup
real_ip_header CF-Connecting-IP;
real_ip_recursive on;
}
```

Revision #1 Created 21 November 2021 20:26:55 by DB T3CH Updated 21 November 2021 20:29:15 by DB T3CH